

**Modification of the file: `fdMD_OneTraj.cmd` for the TEST ( Toy ) example:**

1. The Toy example consist in ten files each one containing 20 snapshots that represent 20ns of MD:

```
2ohk_1_dyn_50.nc ( 20 snapshots )
2ohk_2_dyn_50.nc ( 20 snapshots )
2ohk_3_dyn_50.nc ( 20 snapshots )
2ohk_4_dyn_50.nc ( 20 snapshots )
2ohk_5_dyn_50.nc ( 20 snapshots )
2ohk_6_dyn_50.nc ( 20 snapshots )
2ohk_7_dyn_50.nc ( 20 snapshots )
2ohk_8_dyn_50.nc ( 20 snapshots )
2ohk_9_dyn_50.nc ( 20 snapshots )
2ohk_10_dyn_50.nc ( 20 snapshots )
```

A total of 200 snapshot for 200 ns of MD. Thus, 1 snapshot / ns

2. A topology file:

```
2ohk_Sol_vdw2301_ZeroB.top ( with vdW repulsion between C99 Atoms and
                             Mass Repartitioning )
```

3. A reference file (the first one from the MD):

```
first_lig.pdb
```

**A) First, we need to modify the script:**

- `fdMD_OneTraj.cmd`

The User **MUST** have this structure :

```
# -----
# -  fdMD_OneTraj  -
# -----
#
# AMBER version and directory
set amber_version = 18
set amber_dir = /home/prog/amber$amber_version
set cpptraj = $amber_dir/bin/cpptraj
# Number of Protein residues
# Number of Ligands in the simulation
@ num_res_prot = 387
@ num_lig = 26
# Residues to Superpose
@ ini_res_sup = 1
@ ifi_res_sup = 387
# Refers to the Protein PLUS ONE ligand: Without wat,Na+,Cl-.. but both prepared !!!
# xray can be = yes/no
set xray = 'no'
if ( $xray == 'yes' ) then
  set ref_pdb = "Name_Of_XRay_PDB.pdb"
else
```

NoWat.2ohk_Sol_vdw2301_ZeroB.top	# Topological file for the full trajectory without WAT,ions...but with all the LIGANDS
OneLig.NoWat.2ohk_Sol_vdw2301_ZeroB.top	# Topological file for the full trajectory without WAT,ions...but with ONLY ONE LIGAND
RMS_first.dat	
RMSD_FIRST_NoWat_alone.nc	# The full trajectory ( without WAT, ions..) but with ALL the LIGAND
gen_one_traj.out	# General Info about the process